



Pulse Report — Installation guide

Download, first start, activation — and what the administrator needs to know.

Version 0.1.0 · <https://adatpulzus.hu/pulse-report.html> · info@adatpulzus.hu

What you need

- Windows 10 or Windows 11 (64-bit).
- A browser: Edge, Chrome or Firefox — the program opens in it.
- About 600 MB of free space on the system drive (the program stays unpacked for fast start-up).
- Internet for the first activation and occasionally for the licence check — not continuously.
- **No need** for admin rights, an installer, Excel or any other program.

1. Download

Pulse Report is a single file: **PulseReport.exe**. The download link is in the trial-key email and on the website (<https://adatpulzus.hu/pulse-report.html>). Put it in a folder of your own, for example Documents\Pulse Report — anywhere is fine, Program Files is not needed.

The Windows warning. On first start Windows SmartScreen may say “unknown publisher”. Click **More info**, then **Run anyway**. This is needed once. The program is signed and checks its own integrity at start-up.

2. First start

Double-click the file. The first start takes half a minute to a minute (the program unpacks itself), later ones a few seconds. The program starts a small local service on your PC and opens the address <http://127.0.0.1:...> in your browser — that is not the internet but your own PC. If the browser doesn't open by itself, start the program once more: it opens the address of the instance already running.


3. Activation with the key

On the first screen paste the licence key (PLS-XXXX-XXXX-XXXX-XXXX) and click **Activate**. The trial key comes by email; **click the confirmation link in the email first**, otherwise the key is not yet active. The 30-day trial starts on activation.

No internet on this PC?

Activation works offline too: enter the key, click **No internet on this computer?**, create an **activation request** (a small file), send it to us (info@adatpulzus.hu), and load the licence file you

get back with **Load licence file**. The offline licence is valid for 90 days and can be renewed the same way.



The activation screen

4. Where are my files?

The program keeps everything of its own in this folder:

%LOCALAPPDATA%\Adatpulzus\PulseReport. The licence, saved work, remembered decisions, style profiles, your logo and the log are here. The working copies of loaded files are here only while the program runs. Exported PDF, Excel and image files go to the browser's download folder.

5. Updating and removing

- **Updating:** download the new PulseReport.exe and replace the old one. The program does not update itself — that may be forbidden on company PCs. The old unpacked copy is deleted by the new start-up.
- **Moving to another PC:** on the old one Settings → Licence → switch off, on the new one activate with the same key. Saved work can be carried over from the folder above.
- **Removing:** delete PulseReport.exe and the folder above. Nothing is written into the registry, no service is left behind.

6. Network and security — for the administrator

- The program talks only to **licenc.adatpulzus.hu**, over HTTPS (443), and only about the licence: a hash of the machine identifier, the machine name, the program version. Customer data never goes across.
- The interface runs inside the PC at **127.0.0.1**, on a random port, with a one-time key; it cannot be reached from outside, and nothing needs to be opened on the local firewall.
- No admin rights are needed; the program writes into the user's own folder. Behind a proxy it uses the Windows proxy settings.
- Without a network it works fully for 14 days (with an offline licence file, 90 days); a missing network never blocks anyone.

If something doesn't work

- **Windows won't run it:** SmartScreen → More info → Run anyway. If the antivirus quarantined it, allow PulseReport.exe.
- **The browser doesn't open:** start the program once more; if it still doesn't, open the address in the last line of the log (%LOCALAPPDATA%\Adatpulzus\PulseReport\logs).
- **"The connection was lost":** the program stopped (quit, 20 minutes idle, or the PC slept). Start it again — your saved work is still there.
- **Activation fails:** check that you clicked the confirmation link in the email and typed the key exactly. If the licence already runs on the allowed number of PCs, the program offers which one to switch off.
- **Questions, problems:** info@adatpulzus.hu — tell us what you did and what you saw; the log file (%LOCALAPPDATA%\Adatpulzus\PulseReport\logs) helps, and it contains no customer data.